


**LEGEND**

 Zone of best mineralization

Hole No.	Ft.	Assay
Q92	10' - 300' = 290'	0.64 % Cu
Q93	60' - 90' = 30'	0.36 %
	110' - 120' = 10'	0.37 %
	130' - 140' = 10'	1.53 %
	150' - 160' = 10'	0.69 %
Q94	60' - 100' = 40'	0.24 %
	250' - 300' = 50'	0.74 %
Q95	40' - 50' = 10'	0.16 %
	120' - 130' = 10'	0.13 %
Q96	120' - 140' = 20'	0.41 %
	190' - 240' = 50'	0.37 %
	250' - 280' = 30'	0.54 %
Q97	50' - 60' = 10'	1.01 %
	80' - 90' = 10'	1.71 %
	100' - 110' = 10'	0.45 %
	120' - 170' = 50'	0.80 %
	180' - 190' = 10'	0.60 %
	200' - 210' = 10'	0.35 %
	230' - 270' = 40'	0.42 %
	280' - 300' = 20'	0.55 %
Q98	30' - 130' = 100'	0.14 %
	130' - 300' = 170'	0.66 %
Q99	50' - 300' = 250'	0.67 %
Q100	70' - 90' = 20'	0.63 %
	100' - 110' = 10'	0.33 %

Hole No.	Ft.	Assay
Q100	120' - 130' = 10'	0.22 % Cu
	140' - 150' = 10'	0.18 %
	160' - 170' = 10'	0.25 %
	190' - 210' = 20'	0.18 %
	220' - 250' = 30'	0.44 %
	260' - 300' = 40'	0.29 %
Q101	100' - 110' = 10'	0.20 %
	140' - 150' = 10'	0.22 %
	160' - 170' = 10'	0.35 %
	180' - 220' = 40'	0.61 %
	230' - 240' = 10'	0.33 %
	270' - 300' = 30'	0.91 %
Q102	40' - 150' = 110'	0.36 %
	160' - 300' = 140'	0.65 %
Q103	80' - 90' = 10'	0.37 %
	130' - 300' = 170'	0.69 %
Q104	70' - 300' = 230'	0.45 %
Q105	40' - 300' = 260'	0.87 %
Q106	20' - 300' = 280'	1.03 %
Q107	100' - 300' = 200'	0.56 %
Q108	140' - 190' = 50'	0.31 %
	200' - 270' = 70'	0.27 %
	270' - 300' = 30'	0.12 %

BACON & CROWHURST LTD.

SKETCH SHOWING LOCATION  
(PENDING SURVEY)  
OF

AFTON MINES LTD., (ZONE II)  
PERCUSSION HOLES AND ASSAYS

SCALE 1" = 100 FT.

OCT. 1971

673604